

08-已使用授权用户数

采购的相关产品和插件，都是按授权用户数（用户数级别）来进行收费的，有时候我们需要知道当前已经授权的授权用户数，可以根据以下指引查看

用户数

用户数是指最大活跃的用户数（系统中注册的有效用户，他们可以登录到系统中），当超过此用户数后，系统将变为只读模式。


授权用户可以指产品授权给谁使用，那么他就算一个授权用户，即一个活跃用户。系统中存在的用户，当没有授权给他，或者此账户未被激活，也不算用户数。当一个授权用户被禁用，那么活跃用户数会减1。

JIRA授权

系统管理员登录到JIRA后台，在应用程序→ 程序 访问权中查看


本页内容

- 用户数
- JIRA授权
- Confluence授权
- BitBucket授权



应用程序访问权中，涉及到的用户组中的用户都为被计算

如果用户离职，可以将授权收回，可以在用户列表中设置



注：如果用户从其它用户目录中获得，需要在其它用户目录的源中禁用

Confluence授权

系统管理员登录到Confluence 后台，在“授权详情中查看

授权码细节

以下是您当前许可证的详细信息。您可以访问 my.atlassian.com 管理 Atlassian 许可证。

机构	ww[REDACTED].com
技术支持授权号	SE[REDACTED]04974
服务器ID	BL33-5E[REDACTED]-VU2U (Atlassian可能需要你提供这个信息)
授权类型	Confluence (Server): Evaluation
授权用户数	无限的 (616 当前已注册) 了解更多 Refresh
购买日期	十二月 20, 2020
授权到期日	您的[REDACTED] 21:00到期。

被授权的用户数，可以在全局权限中查看，在全局权限中设置的定用户组和指定组，都算授权用户数

授权用户数

组

组权限-全局

		个人空间 [?]	创建空间 [?]	站点管理 [?]	系统管理员 [?]
HKT-X-CORE	✓ 可用	✗	✗	✓	✓
HKT-X-管理员	✓ 可用	✗	✗	✓	✓
confluence-administrators	✓ 可用	✓	✓	✓	✓
confluence-users	✓ 可用	✗	✗	✗	✗
jira-administrators	✓ 可用	✗	✗	✗	✗

用户

用户权限-全局

		个人空间 [?]	创建空间 [?]	站点管理 [?]	系统管理员 [?]
admin (admin)	✓ 可用	✗	✓	✓	✓

BitBucket授权

系统管理员登录到BitBucket后台，在“授权详情”中查看

License Settings

Support and updates for Atlassian Bitbucket will end on 19 Jun 2021. Updates released after this date will not be valid with this

Server ID **B0HP-9HLE-J78H-992D**

License

License **Bitbucket** **ers: Commercial Term License**

Licensed to

Support Entitlement Number (SEN) **St** **314**

Expires **21**

User limit **25**

Licensed users **4**

Clustering **Available**

[Edit license](#)