

Gears space group for confluence

Gears space group for confluence

允许空间管理员管理在本空间中创建的用户组，以及对这些组中的人员管理，以此进行分级管理，减少对系统管理员的依赖

It allows the space administrator to manage the user groups created in the space and account in these groups, so can management and reduce the dependence on the system administrator

The screenshot shows the 'Space Tools' interface with the 'Space Group' tab selected. Below the navigation bar, there are sub-tabs for 'Space Group', 'Membership', and 'User'. A 'New Group' form is visible, consisting of a text input field and a 'Create' button. Below the form is a table listing existing groups:

Group	Action
ds-hktx	Remove
ds-seven	Remove
ds-maya	Remove

空间中添加用户组

Add user group in space

The screenshot shows the 'Space Tools' interface with the 'Membership' tab selected. It features a form to add users with a dropdown menu for selecting a group (currently 'ds-hktx'), a 'Username' input field, and an 'Add' button. Below the form is a table listing current members:

Username	Fullname	Email	Action
user02	user02	user02@hktx.cn	Remove
user03	user03	user03@hktx.cn	Remove

对空间组中的用户进行管理

Manage users in a space group

Space Tools

Overview Permissions Content Tools Look and Feel Audit log Integrations Space Group

Space Group Membership User

Username

user01

Query

Group

ds-hktx

ds-seven

ds-maya

查看用户所在空间组并管理

View users' space groups and manage them

Space Tools

Overview Permissions Content Tools Look and Feel Audit log Integrations Space Group

Group Members User Tools

System Group

will add to

Space Group

Execute

System Group

will remove from

Space Group

Remove

允许空间管理员将一个组中的成员批量加入到空间组中

Allows space administrators to batch add members from a group to a space group

Enabled Spaces

Enabled Spaces

Enabled Spaces:

Demonstration Space

系统管理员可以决定在哪些空间组中使用此功能

The administrator can decide that this function can be enabled in such a space

说明

- 系统管理员、Confluence管理员可以在：一般配置-》用户&安全-》空间组 管理员针对哪些空间启动此功能
- 只有空间管理员（具体空间管理权限）才能够看到管理菜单，并能够对用户组及组中的用户进行管理
- 为了区别不同空间中的用户组，在添加组的时候，会在填写的组名前增加空间的键值(KEY)
- 空间管理员只能管理自己空间创建的用户组
- 添加的用户组会增加到系统中的内置目录用户组中。
- 空间中创建的用户组可以被其它空间在权限管理、页面权限中使用（与系统中的组使用无差别）

explain

- System administrators or confluence administrators can enable this function in general > **Users & Security**> **space group** of management background
- Only the space administrator (specific space management authority) can see the management menu and manage the users and the users in the group
- In order to distinguish groups in different spaces, when adding a group, the key value of the space will be added before the group name filled in
- Space administrators can only manage user groups created by their own spaces
- The added groups will be added to the built-in Directory in the system.
- The group created in the space can be used by other spaces in permission management and page permission (no difference from the group in the system)